

NANO 60

BRUNETTE FORMULA

Professional Directions

PARABEN-FREE

FORMALDEHYDE-FREE

VEGAN

1

HAIR PREPARATION

5–10 min

Evaluate the hair condition before beginning the service. The hair must be clean, dry, and detangled. Shampoo only if there is visible product build-up or excess oil.

Do not use clarifying shampoo unless necessary, as it can over-open the cuticle and affect product performance.

KEY: Apply to dry hair – no pre-wash unless build-up present

2

PRODUCT APPLICATION

10–20 min

Shake the NVL NANO60 bottle thoroughly before use. Apply to dry hair using a brush and comb-through method, starting one finger’s width from the scalp and working evenly to the ends.

Ensure full saturation without excess – hair should feel coated but not dripping.

AMOUNT: Pour 30–70 ml depending on length and density

3

PROCESSING TIME

45–90 min

Allow the product to process for 60–90 minutes, depending on hair texture and density. Perform a strand test to confirm readiness before rinsing.

FINE
45–60 min

MEDIUM
60 min

RESISTANT
75–90 min

Strand test midway for flexibility. No heat during processing.

4

RINSE

Rinse hair with lukewarm water, removing 80–90% of the product. Leave a slight residue in the hair to maintain slip and control during the drying phase.

IMPORTANT: Light slip helps activation — do not rinse completely

5

BLOW-DRY

Blow-dry the hair completely using a paddle brush or tension technique. Work in sections and direct airflow downward to help smooth and align the cuticle for an even finish.

TARGET: 100% dry — cuticle alignment = smoother seal

6

HEAT ACTIVATION

Use a titanium straightening iron. Work in fine, consistent sections. Pass the iron 5–20 times per section until the cuticle is sealed and desired smoothness is achieved.

For best results, apply NVL Heatshield Primer before ironing to protect and enhance shine.

COARSE /
RESISTANT

210–230°C

15–20 passes

NORMAL /
NATURAL

190–210°C

10–15 passes

FRAGILE /
DAMAGED

150–170°C

7–10 passes

7

RINSE & AFTERCARE

After ironing, allow the hair to cool for several minutes before rinsing. Rinse thoroughly with lukewarm water.

Apply NVL Anti-Frizz Conditioner to rebalance pH and seal the treatment. Rinse well, then complete with NVL Anti-Frizz Shampoo followed by a final application of conditioner.

1

NVL Anti-Frizz Conditioner

2

NVL Anti-Frizz Shampoo

3

Final Conditioner rinse

8

FINISH & MAINTENANCE

Blow-dry the hair to the desired finish. Advise clients to avoid washing, tying, or wetting the hair for 48 hours post-treatment to ensure full sealing and long-lasting results.

For ongoing care, recommend the NVL Anti-Frizz Home Maintenance range to preserve smoothness, hydration, and shine.

CLIENT TAKE-HOME ADVICE

- No washing, tying, or wetting for 48 hours
- Colour best applied 5–7 days post-treatment
- Use NVL Anti-Frizz Shampoo + Conditioner
- Sulphate-free care extends results
- Repeat every 12–16 weeks for progressive improvement
- Results last 3–6 months with proper care

AT A GLANCE

01

PREPARE

Assess hair condition.
Dry, clean, detangled.
Shampoo only if needed.

02

APPLY

Brush + comb on dry hair. 1 finger width from scalp. 30–70 ml.

03

PROCESS

Fine 45–60 min.
Medium 60 min.
Resistant 75–90 min.

04

RINSE

Lukewarm water.
Remove 80–90%.
Leave slight residue.

05

BLOW-DRY

Dry 100% with paddle brush. Direct airflow downward.

06

IRON

Titanium iron.
5–20 passes per section. See temps.

07

RINSE & CARE

Cool, rinse, condition, shampoo, condition again.

08

FINISH

Blow-dry to finish.
No wash/tie/wet for 48 hours.

IRON TEMPERATURE

Coarse / Resistant

210–230°C 15–20 passes

Normal / Natural

190–210°C 10–15 passes

Fragile / Damaged

150–170°C 7–10 passes

AFTERCARE

- No wash/tie/wet for 48 hours
- Colour 5–7 days post-treatment
- NVL Anti-Frizz range for home care
- Repeat every 12–16 weeks
- Results last 3–6 months with care

SAFETY

- Professional use only
- Wear gloves throughout
- Avoid direct scalp contact
- Ensure adequate ventilation
- Patch and strand test required